

Allegro[®] Free Physical Viewer

Product Version 23.1
September 2023

© 2023 Cadence Design Systems, Inc. All rights reserved.

Portions © Apache Software Foundation, Sun Microsystems, Free Software Foundation, Inc., Regents of the University of California, Massachusetts Institute of Technology, University of Florida. Used by permission. Printed in the United States of America.

Cadence Design Systems, Inc. (Cadence), 2655 Seely Ave., San Jose, CA 95134, USA.

Allegro PCB Editor contains technology licensed from, and copyrighted by: Apache Software Foundation, 1901 Munsey Drive Forest Hill, MD 21050, USA © 2000-2005, Apache Software Foundation. Sun Microsystems, 4150 Network Circle, Santa Clara, CA 95054 USA © 1994-2007, Sun Microsystems, Inc. Free Software Foundation, 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA © 1989, 1991, Free Software Foundation, Inc. Regents of the University of California, Sun Microsystems, Inc., Scriptics Corporation, © 2001, Regents of the University of California. Daniel Stenberg, © 1996 - 2006, Daniel Stenberg. UMFPACK © 2005, Timothy A. Davis, University of Florida, (davis@cise.ulf.edu). Ken Martin, Will Schroeder, Bill Lorensen © 1993-2002, Ken Martin, Will Schroeder, Bill Lorensen. Massachusetts Institute of Technology, 77 Massachusetts Avenue, Cambridge, Massachusetts, USA © 2003, the Board of Trustees of Massachusetts Institute of Technology. All rights reserved.

Trademarks: Trademarks and service marks of Cadence Design Systems, Inc. contained in this document are attributed to Cadence with the appropriate symbol. For queries regarding Cadence's trademarks, contact the corporate legal department at the address shown above or call 800.862.4522.

Open SystemC, Open SystemC Initiative, OSCI, SystemC, and SystemC Initiative are trademarks or registered trademarks of Open SystemC Initiative, Inc. in the United States and other countries and are used with permission. All other trademarks are the property of their respective holders.

Restricted Permission: This publication is protected by copyright law and international treaties and contains trade secrets and proprietary information owned by Cadence. Unauthorized reproduction or distribution of this publication, or any portion of it, may result in civil and criminal penalties. Except as specified in this permission statement, this publication may not be copied, reproduced, modified, published, uploaded, posted, transmitted, or distributed in any way, without prior written permission from Cadence. Unless otherwise agreed to by Cadence in writing, this statement grants Cadence customers permission to print one (1) hard copy of this publication subject to the following conditions:

1. The publication may be used only in accordance with a written agreement between Cadence and its customer.
2. The publication may not be modified in any way.
3. Any authorized copy of the publication or portion thereof must include all original copyright, trademark, and other proprietary notices and this permission statement.
4. The information contained in this document cannot be used in the development of like products or software, whether for internal or external use, and shall not be used for the benefit of any other party, whether or not for consideration.

Disclaimer: Information in this publication is subject to change without notice and does not represent a commitment on the part of Cadence. Except as may be explicitly set forth in such agreement, Cadence does not make, and expressly disclaims, any representations or warranties as to the completeness, accuracy or usefulness of the information contained in this document. Cadence does not warrant that use of such information will not infringe any third party rights, nor does Cadence assume any liability for damages or costs of any kind that may result from use of such information. Cadence is committed to using respectful language in our code and communications. We are also active in the removal and/or replacement of inappropriate language from existing content. This product documentation may however contain material that is no longer considered appropriate but still reflects long-standing industry terminology. Such content will be addressed at a time when the related software can be updated without end-user impact.

Restricted Rights: Use, duplication, or disclosure by the Government is subject to restrictions as set forth in FAR52.227-14 and DFAR52.227-7013 et seq. or its successor.

Contents

1

<u>Getting Started with Allegro Free Physical Viewer</u>	7
<u>Opening Design in Allegro Free Physical Viewer</u>	7
<u>Allegro Free Physical Viewer User Interface</u>	9
<u>Visibility Panel</u>	10
<u>Layers Tab</u>	10
<u>Objects and Areas Sub Section</u>	12
<u>Geometries Sub Section</u>	13
<u>Components Sub Section</u>	14
<u>Manufacturing Sub Section</u>	17
<u>Rigid Flex Sub Section</u>	19
<u>Surface Finish Sub Section</u>	20
<u>Data Layers Sub Section</u>	20
<u>Nets Tab</u>	21
<u>Nets Sub Sections</u>	22
<u>Display Tab</u>	24
<u>General Sub section</u>	24
<u>Shadow Settings Sub Section</u>	25
<u>Opacity Sub Section</u>	25
<u>Properties Panel</u>	25
<u>Selection Filter Sub Section</u>	26
<u>Properties Tab When No Object is Selected</u>	26
<u>Status Sub Section</u>	26
<u>Grids Sub Section</u>	27
<u>Parameters Sub Section</u>	28
<u>Attributes Sub Section</u>	29
<u>Properties Tab When One or More Objects are Selected</u>	29
<u>Arrange Sub Section</u>	29
<u>Location Sub Section</u>	29
<u>General Sub Section</u>	30
<u>Attributes Sub Section</u>	31

Allegro Free Physical Viewer

<u>Properties Tab For a Symbol</u>	32
<u>Constraints Tab</u>	34
<u>Object Constraints Sub Section</u>	35
<u>Search Panel</u>	36
<u>Filtering Search From Canvas</u>	38
<u>Filtering Search From Properties Panel</u>	39

2

<u>Working With Allegro Free Viewer</u>	41
<u>Viewing Objects From Search Results</u>	41
<u>Selecting Objects From Canvas Using Selection Filter</u>	42
<u>Viewing Net Objects in a Design</u>	43
<u>Assigning Color to Net Objects</u>	44
<u>Viewing Object Properties In Datatips</u>	46
<u>Viewing Dynamic Etch Shape Parameters</u>	47
<u>Viewing Pin and Via Parameters</u>	49
<u>Viewing Constraint Resolution Between Two Objects</u>	51
<u>Viewing Design in 3D Canvas</u>	52
<u>Measuring Distance Between Objects</u>	54
<u>Generating Prints</u>	55
<u>Capturing Canvas Image</u>	56
<u>Recording and Replaying Script</u>	57

3

<u>Menus and Commands</u>	59
<u>File Menu Commands</u>	59
open	59
<u>Open File Browser Dialog Box</u>	60
plot	61
plot setup	61
<u>Plot Setup Dialog Box</u>	61
plot preview	63
script	63
<u>Scripting Dialog Box</u>	64
exit	65

Allegro Free Physical Viewer

<u>View Menu Commands</u>	66
<u>zoom commands</u>	67
<u>redraw</u>	67
<u>3d</u>	68
<u>show waived drcs</u>	68
<u>blank waived drcs</u>	69
<u>showhide window commands</u>	69
<u>reset dockwindows</u>	70
<u>Tools Menu Commands</u>	71
<u>capture image</u>	71
Menu Path	71
<u>xsection</u>	71
Menu Path	71
<u>custom datatips</u>	72
Datatips Customization Dialog Box	72

4

<u>Troubleshooting</u>	77
<u>What is the minimum system requirement to install Allegro Free Physical Viewer?</u>	77
<u>What are the different versions of Allegro Free Physical Viewer available?</u>	78
<u>Is there any standalone Allegro Free Physical Viewer available for Linux or UNIX OS?</u>	78
<u>Is it possible to cross-probe between Allegro Design Entry HDL to Allegro Free Physical Viewer?</u>	78
<u>What is the difference between Allegro Free Physical Viewer and Allegro Physical Viewer Plus?</u>	78
<u>Is there any Allegro Free Physical Viewer available when I install OrCAD and Allegro (SPB) products? If yes, how can I access it?</u>	79
<u>Why Allegro Free Physical Viewers 2022 aborts while installing?</u>	80
<u>How to enable OpenGL in Allegro Free Physical Viewer?</u>	80
<u>Can SKILL be run on Allegro Free Physical Viewer?</u>	80
<u>How to use the Alt key for selecting a single layer in the Visibility panel on Linux machines?</u>	81
<u>Error Messages and Solution</u>	82
<u>Error: This application has failed to start because its side-by-side configuration is incorrect.</u>	82

Allegro Free Physical Viewer

<u>“ERROR (SPMHOD36): Cannot open drawing” reported when opening designs using Allegro/Sip FREE Physical Viewer</u>	82
<u>ERROR 1152: Error extracting to the temporary location</u>	83

Getting Started with Allegro Free Physical Viewer

The Cadence® Allegro® X/OrCAD® X FREE Physical Viewer is a free downloadable application that can be used by design engineers, manufacturing units, and by customers to review the design files at different phases of design. This application allows you to view and plot databases from Allegro X PCB Editor, OrCAD X PCB Editor, Allegro X Package Designer, and Allegro X PCB SI technology.

It enables you to review the physical design, monitor its progress, assess fabrication and assembly requirements to ensure design specifications are met. Allegro Free Physical Viewer provides all the key features of layout editors required to review a design. You can pan, zoom, highlight, search, assign color to objects and preview the design in 3D using Allegro Free Viewer.

Opening Design in Allegro Free Physical Viewer

To open a layout design in Allegro Free Physical Viewer, follow these steps:

1. Launch the free viewer by selecting *Start – Cadence PCB Viewers 2023 – PCB Editor Viewer 2023*.
2. To launch the free viewer from the command line, type `allegro_free_viewer` in a command window and press `Enter`.

Allegro Free Physical Viewer window opens with a blank design.

3. Choose *File – Open* and select a file to open in free viewer. The supported designs file types are board (`.brd`), design partition (`.dpf`), module definition (`.mdd`), and symbol drawing (`.dra`).

Allegro Free Physical Viewer


Getting Started with Allegro Free Physical Viewer



Tip

You can choose to open default Cadence board design file (Cadence_Demo.brd) from the installation hierarchy. This design file is located at
`<installation_hierachy>\share\pcb\examples\board_design`

The design is always opened in read-only mode and is non-editable. The following image displays default Cadence board design file (Cadence_Demo.brd) in Allegro Free Physical Viewer.




Allegro Free Physical Viewer User Interface

The user interface of Allegro Free Physical Viewer can be divided into three key sections. The left panel is the visibility panel, that has controls for managing the display settings and for modifying the visibility of various design objects such as nets, layers, and objects.

Design canvas is at the center of the application window and displays the physical layout. All your design activities are completed in this section. Just below the design canvas Search window is displayed that lists all the design objects in a spreadsheet format.




The right most panel is the properties panel, that displays the properties and constraint based on the current selection in the canvas.



This section walks you through the main elements of user interface. Understanding the architecture would help you easily interact with the application in a natural and intuitive way.

Visibility Panel

When reviewing a design you can enable or disable the visibility of each design object explicitly using the Visibility panel. It has three tabs that lets you control:

- Layers : Visibility of layers and assign color to layers and objects
- Nets : Visibility of nets and assign color to nets
- Display : Display settings

Layers Tab

When you open a design, by default the Layers tab is opened in the Visibility panel. All the layers and objects are visible in the design canvas and the primary stackup is selected. The subsequent collapsible sub sections *Objects & Areas*, *Geometries*, *Components*, *Manufacturing*, *Rigid Flex*, *Surface Finishes* and *Data Layers* display only those layers and objects that are defined in the primary stackup.


At the top, the following three options are provided that can be selected exclusive of each other:

- *All Layers*: Turns on or off the global visibility
- *Layer Stackup*: Selects stackup other than the primary stackup.
- *Views*: Selects existing view. Lists film generated from artwork.

Allegro Free Physical Viewer


Getting Started with Allegro Free Physical Viewer

Depending on which stackup and view is selected the corresponding sub sections dynamically update and displays relevant layers and objects.





To reset to default view and layer stackup, click the *On* button for *All Layers*.

The toggle eye icon  at the header of sub section turns on or off the visibility of all the items under that sub section. Visibility of any object can be simply turned on or off by enabling or disabling the color box associated to objects for any layer. The color box also indicates the custom color assigned to the object on that layer. Right-click color box to open a color palette and you can choose a different color that gets immediately assigned to the object on that layer.

Objects and Areas Sub Section

Objects & Areas sub section lists all the design layers including mask and silkscreen layers. It has filters for both layer types and object types. You can set layer filter for *Signals*, *Planes*, *Dielectrics*, and *Masks*. Using color box you can turn on or off individual objects on design layers. You can also assign color and turn on or off visibility of each object per layer.


The color box acts as a toggle and controls the visibility of an object on a layer. To change the color assignment of any object right-click the color box. The following is a simple explanation of color box representation in:

- Solid color box: Indicates that the object is visible on that layer.
- Hollow box with colored outline: Indicates that object is not visible on that layer. The color of outline displays the color assigned to that object on the selected layer.
- Solid gray box: Indicates that object is visible on all layers. Different or the same colors are assigned to object on each layer.
- Hollow box with gray outline: Indicates that object is not visible on all the layers and have different colors assigned to each layer.

Allegro Free Physical Viewer

Getting Started with Allegro Free Physical Viewer

- Solid gray box with outline: Indicates that object is visible on some of the layers and have different colors assigned to each layer.



Filter by Layer

Filter by Object

Solid gray box
(Object is visible on all the layers)

Solid gray box with outline
(Object is visible on some layers)

Hollow gray box
(Object is not visible on all the layers)

Hollow color box
(Object is not visible on the selected layer)

Solid color box
(Object is visible on the selected layer)

Design Outline visibility control



Tip

To select a single object, press **ATL** key and click the color box.

A separate toggle is provided at the bottom of the section to control the visibility of design outline.


Geometries Sub Section

Geometries sub section controls the visibility of board geometry class, such as outline, dimension, and keepin areas in the design canvas. The first part of the section displays user-

Allegro Free Physical Viewer

Getting Started with Allegro Free Physical Viewer

defined board geometry layers. You can also assign color at any time using the color box attached with each geometry.




Components Sub Section

Components sub section controls the visibility of component geometry class/subclass and package geometry class/subclass. This section consists of two tables of layers representing

Allegro Free Physical Viewer

Getting Started with Allegro Free Physical Viewer

top and bottom component visibility controls. Layers Assembly, Pastemask, Silkscreen, Soldermask, Place_Bound and Dfa_Bound are defined as rows, and objects Pin, RefDes, Line, Shape and Text are columns.





Manufacturing Sub Section

Manufacturing sub section controls the visibility of layers of manufacturing class, such as autosilk, ncd drill, and so on. The display of holes can also be controlled in the sub section. The

Allegro Free Physical Viewer

Getting Started with Allegro Free Physical Viewer

first part of the section displays user-defined manufacturing layers. You can also assign color at any time using the color box attached with each layer.





Allegro Free Physical Viewer

Getting Started with Allegro Free Physical Viewer


Rigid Flex Sub Section

Rigid Flex sub section controls the visibility of all rigid flex layers, such as bend area, bend line, coverlay, and so on. You can also assign color at any time using the color box attached with each rigid flex layer.




Surface Finish Sub Section

Surface Finish sub section controls the visibility of all layers added to surface finish class. The surface finish layers are added to define finished materials used on a design such as tin plating, gold, Organic Solderability Preservative (OSP), and so on. You can assign color at any time using the color box attached with each surface finish layer.



Data Layers Sub Section


Data Layers sub section lists other classes and subclasses. It also displays layers for Drawing Format class and user-defined subclass. You can control the visibility and color settings of user-defined layers in this sub section.






Nets Tab


The *Nets* tab lists nets by net group, match group, net class, bus, differential pair, XNet, and net in different collapsible sub sections. Members of each group are listed in hierarchical order all the way down to nets. In this tab, you can turn on or off the visibility and assign color to individual nets or group of nets.

Each group of net object can be identified by unique icon. Clicking the icon expand and collapse the group element to its immediate members. The white color of icon indicates that a group is expanded and shows all its members nets. When collapsed the icon turns gray.



The icon  indicates that visibility state is enabled and the net connection is visible in the design canvas. The icon color changes to white when the visibility is turned off. Clicking on individual  icon toggles the connection visibility on or off of that net object. Any change in the visibility of a parent net is applied to its member nets. If the same parent net and its members are also in other *Nets* sub sections, those sections also update. The visibility of groups of nets can be controlled by toggling the header  icon.


Double-click a net object highlights that net object and zooms to its location in the design canvas.

The color box indicates the custom color state of the net object. When no color is assigned a hollow gray box with a dash inside  is displayed. Assigning color to a parents net applies to that net and all its member nets. Similarly, assigning color to a member net also updates

Allegro Free Physical Viewer

Getting Started with Allegro Free Physical Viewer

the color of parent net. If the same parent or member net is part of other sub sections, then the color assignment is reflected in all the sub sections of *Nets* tab.



The connection visibility and color assignment can be controlled in a design through two global controls:

- **All Connections:** Turns on or off the connection visibility (display of rats) of all the net objects in all the sub sections.
- **Net Colors:** Resets all colors and patterns assigned to net objects for custom color and highlight.

Nets Sub Sections

Nets are categorized under four sub-sections:




Groups




Lists net groups, net classes, match groups, and buses. Clicking on icon toggles to expanding or collapsing immediate members below the group.

Allegro Free Physical Viewer

Getting Started with Allegro Free Physical Viewer

<i>Diff Pairs</i>		Lists differential pairs. Can be a member of <i>Groups</i> . Clicking on icon toggles to expanding or collapsing immediate member nets.
<i>XNets</i>		Lists XNets. Can be a member of <i>Groups</i> and <i>Diff Pairs</i> . Clicking on icon toggles to expanding or collapsing immediate members.
<i>Nets</i>		Lists nets. Can be a member of <i>Groups</i> , <i>Diff Pairs</i> , and <i>XNets</i> .

The color and visibility controls are also available as right-click options. The following options are accessible on an individual net object.




Allegro Free Physical Viewer

Getting Started with Allegro Free Physical Viewer

Display Tab

The *Display* tab provides settings to control the display of objects in the design canvas. You can choose display options from three sections: *General*, *Shadow Settings* and *Opacity*.



General Sub section

This section controls the on screen design display. You can set the following:

View From	Flips the design along the Y-axis on the drawing canvas by selection <i>Top</i> and <i>Bottom</i> . OpenGL must be enabled for this option to work.
Pads	Controls display of pads. By default pads are filled in the design.

Allegro Free Physical Viewer

Getting Started with Allegro Free Physical Viewer

Colors	Assigns custom color to connections (rats), drill holes, backdrill hole, alignment guides, and for temporary highlight.
Net Labels	Displays net names on shapes, traces, pins, and vias. OpenGL must be enabled for this option to work
Other Labels	Displays via label on top of each blind/buried via, indicating the from-to subclasses spanned by the via. OpenGL must be enabled for this option to work.

Shadow Settings Sub Section

Enable shadow mode and adjust brightness and saturation of non-selected objects in the shadow mode. When enabled, selected objects are not affected at all. Whereas non-selected objects are dimmed and the degree of dimming can be controlled by the brightness and saturation sliding bars. The location of slider handle is also represented as percentage value that can be edited by double-clicking the field.

Opacity Sub Section



Sets opacity for objects. You can assign varying degrees of transparency to traces, shapes, vias, pins, and text in the entire design. Sliding the bar completely to the left causes previously filled geometry, such as shapes, to display with less intensity.

The global value is always equal to the highest percentage value set for any object. The percentage value represent the equivalent of the slider handle location. You can double-click the value and enter a new value for opacity.

Note: OpenGL must be enabled for controlling opacity of the design.

Properties Panel


The *Properties* panel provides access to general information, attributes, and constraints. This panel contains two tabs:

- Properties 
- Constraints 

Depending on number of objects selected in canvas these tabs display information in sub sections. In both the tabs, *Selection Filter* sub section is always visible.

Selection Filter Sub Section

To select design objects for viewing in canvas you can use *Selection Filter*. You can select multiple object filters at a time. Only objects enabled in the selection filter can be selected in the canvas. The selected filters are seen in blue color and displays count for each of the objects selected. The *All Objects* option enables and disables all the objects from the filter and provides a summary count of all the objects selected in the canvas. By default, *Groups* filter is disabled.



The *Selection Filter* is available with both properties and constraint tabs of *Properties* panel. The filter is always visible even when no object is selected in the canvas.

Note: The *Selection Filter* is the same as *Find filter* in layout editors with a slight difference in the object filter names. In *Selection Filter*, connections corresponds to ratsnest, traces are clines, gates are functions, wires are bondwires, virtual points are Rat Ts, and components are symbols.

Properties Tab When No Object is Selected

When no object is selected the only *Properties* tab is visible and the *Constraint* tab is hidden. The *Properties* tab provides database-centric information in two four sections: *Status*, *Grids*, *Parameters*, and *Attributes*.

Status Sub Section


Displays design status information of the active design. This sub section provides the details on unplaced components, unrouted nets and connections, shapes, and DRCs.


- Components and nets: A progress bar indicates the percentage and number indicates value. Clicking hyperlink value produces search results for components, pins, or nets in the *Search* panel.

Allegro Free Physical Viewer

Getting Started with Allegro Free Physical Viewer

- **Shapes:** Displays the number of shapes on nets without connections (shape islands), the number of copper shapes unassigned to a net and the number of non-smooth dynamic shapes.
- **DRC:** Indicates whether DRC markers are up-to-date. This section also displays the count of waived DRC errors, net short errors, and waived net short errors that exist in the design.

A white color text and  icon indicates that shapes or DRCs are out of date and require update. Dim text and 0 value indicates status is up-to-date.



Status

Unplaced Components	0/181
Unrouted Nets	1085/1609
Unrouted Connections	3075/3081
Isolated Shapes	24
Unassigned Shapes	0
Out of Date Shapes	22
DRC Errors	476
Shorting Errors	0
Waived Errors	0
Waived Shorting Errors	0

Search Results

NET	TYPE	NET CLASS	DIFF PAIR
1	Signal		
2	Signal		
3	Signal		
3_3V	Power	DEFAULT_3_3V	
3_3V_FB2	Power		

Status is out of date

Status is up to date

Grids Sub Section


This section provides the ability to control grid settings. The options are available to enable or disable the display of grids, type, color, and define grid values.

- *Dots, Lines, or Both* enable the display of grids.
- The current grid unit is displayed, which can be changed using a toggle button.
- The color box displays color assigned to the grid. Clicking the box opens a color palette, and you can choose a different color that gets immediately applied to the grid.
- The grid values can be chosen from preset values for Major and Minor grids or can be customized. Selecting a Major preset value automatically updates the Minor preset value.
- To configure the grid with user-defined values, click on *Custom*. In the *Custom* section, specify *Minor(x,y)* and *Major(x,y)* grid values. The *Major* value can adjust a maximum

Allegro Free Physical Viewer


Getting Started with Allegro Free Physical Viewer

of 20 *Minors*. Entering a *Major* value greater than twenty times of *Minor* is considered invalid. A tool tip is displayed, and the *Major* value is auto-set to its maximum, which is twenty times the *Minor* value.




Parameters Sub Section

This section provides information on database units, accuracy, drawing size and extents. The current design values are indicated in blue color and rest of the fields are not highlighted.



Attributes Sub Section

This section displays properties attached to selected objects. This section is blank when nothing is selected in the design canvas.




Properties Tab When One or More Objects are Selected

Design objects when selected in the canvas displays information in the *Arrange*, *Location*, *General*, and *Attributes* sub sections of the *Properties* tab. When one or more objects are selected *Constraint* tab is also displayed. Depending on the type and number of selected objects, the information which is common to all the selected objects is displayed in the sub sections of the *Properties* tab.


Arrange Sub Section

The *Arrange* sub section display controls for editing objects including rotate, align, flip, mirror. This section remains inactive and non-editable for any selected object.



Location Sub Section

This section is always visible when one or more objects are selected in the design canvas. It displays the layer of the selected object, its X and Y coordinates, and the angle of rotation. The location information is locked and is non-editable. When more than one objects are selected, the common values are displayed and different values are indicated with [...]



Allegro Free Physical Viewer

Getting Started with Allegro Free Physical Viewer


General Sub Section

General sub section is always visible when one or more objects are selected in the design canvas and displays information on the selected objects.

Depending on the object type this section dynamically updates the information.

- When more than one objects of the same type are selected, the common values are displayed and different values are indicated with [...].
- When more than one objects of different types are selected, the common fields are displayed and different values are indicated with [...]. When no field is common across all the selected objects the *General* sub section remains blank.

Clicking a hyperlink value act as a search input and show relevant information in the *Search* window.



Hyperlink Text Invokes Search Results

Search

UPD431000AGW-B15_SOJ127P866X375-32N_IC_UPD431000AGW-B15_PSL-00000035


Reset

Components (8)

	REFDES	PART NUMBER	FOOT PRINT	LAYER	ROTATION	MIRROR
U43	U43	UPD431000AGW-B15_SOJ127P866X...	SOJ127P866X375-32N	Top	0.000°	NO
U44	U44	UPD431000AGW-B15_SOJ127P866X...	SOJ127P866X375-32N	Top	0.000°	NO
U45	U45	UPD431000AGW-B15_SOJ127P866X...	SOJ127P866X375-32N	Top	0.000°	NO
U46	U46	UPD431000AGW-B15_SOJ127P866X...	SOJ127P866X375-32N	Top	0.000°	NO
U47	U47	UPD431000AGW-B15_SOJ127P866X...	SOJ127P866X375-32N	Top	0.000°	NO

Attributes Sub Section

Displays properties attached to selected objects. This section displays both the system-defined and user-defined attached to selected objects. When multiple objects are selected only the common properties are displayed.



NAME	VALUE
MECH_PIN_TO_CONDUCT...	0.127 MM
MECH_PIN_TO_MECH_PIN...	0.127 MM
ROOM	MEM
<add attribute>	


A blank row is displayed when no properties are defined no common properties are found for the selected objects.

Properties Tab For a Symbol

When a symbol (.dra) is opened, the *Status* section of the *Properties* tab provides symbol information that includes pin information, padstack data, 3D model assigned to it, and so on.

Allegro Free Physical Viewer

Getting Started with Allegro Free Physical Viewer




Allegro Free Physical Viewer

Getting Started with Allegro Free Physical Viewer

Constraints Tab

When an object that has constraints assigned is selected in the design canvas the *Constraints* tab becomes visible. The *Selection Filter* is also available with this tab and lets you filter the object types.



The *Constraints* tab is not displayed, if in the design canvas:

- More than 2 objects are selected

- Selected object does not have any constraint applied to it

Object Constraints Sub Section

This sub section displays constraint information of the selected objects. The following can be displayed:

- Object Name and Type
- Resolved Level
 - ☐ Physical: When single object is selected
 - ☐ Spacing: When two objects are selected
- Electrical Constraint: When at least one net is selected
- Value: When trace segment is selected

Allegro Free Physical Viewer

Getting Started with Allegro Free Physical Viewer

- Air Gap: When two objects are selected

The screenshot shows the Properties panel with the Selection Filter set to 'All Objects (2)'. The Object Constraints section displays constraints for two objects: Object1 (Net - DATA2+) and Object2 (Trace Segment - DATA2-). The constraints are listed in a table below.

Resolved Level	Constraint Set	Constraint	Value
DiffPair	DIFF1	Differential Pair Primary Gap	0.127 MM
DiffPair	DIFF1	Differential Pair Neck Gap	0.117 MM
DiffPair	DIFF1	Differential Pair Coupled To...	0.01 MM
DiffPair	DIFF1	Differential Pair Coupled To...	0.01 MM
DiffPair	DIFF1	DiffPair Minimum Gap	0.107 MM

Electrical Constraints

relative prop delay: global group DATA_DIFFS from AD to AR delta=0.000 MM tol=2.540 MM
(RDly) U1.B5 to U2.D6 min= 24.618 MM max= 29.698 MM actual= 27.283 MM target= (DATA1+) U1.D6 to U2.D5
(SPhase) U1.B5 to U2.D6 actual= 27.283 MM
DPData: gap=0.127 (-0.001,+0.000) tolerance= ; max uncoupled= -0.001


Search Panel

The *Search* panel lets you locate an object in the design. When a design is opened first time many object tabs are displayed in the *Search* panel. The active tab is displayed in blue color. Each tab shows the total count of that object type and a list of objects in a spreadsheet format.

Allegro Free Physical Viewer

Getting Started with Allegro Free Physical Viewer

The columns of spreadsheet represents properties of that object type. You can resize, rearrange and filter information in each column.



A search bar is displayed just above the spreadsheet to filter the results table. When you search a text or number string only the rows that matches the search string are displayed. Clicking a cell, selects the complete row. You can bring the focus to search bar at any time using keyboard shortcuts **CTRL+F** or by pressing **F3** key.


Double-click an object selects the corresponding object in the design canvas. To select multiple objects in the canvas, you can use right-click option *Select on Canvas*. Click anywhere in the blank space in the design canvas deselects the objects.

Allegro Free Physical Viewer

Getting Started with Allegro Free Physical Viewer

Filtering Search From Canvas

When you right-click on selected objects in the design canvas and choose *Show in Search*, the spreadsheet populates the information of the selected objects and a custom search string *Canvas Search* is displayed in the *Search* panel.



Allegro Free Physical Viewer

Getting Started with Allegro Free Physical Viewer

Filtering Search From Properties Panel

Clicking a hyperlink value in the *Properties* panel filters the *Search* for that value. All the objects tabs are filtered and only those are displayed that matches with the filter value.

The screenshot shows the Allegro Free Physical Viewer interface. On the left is the 'General' Properties panel, which is locked. It contains fields for Group, Net (N00048_USER_DESIGN_OUT), Pin # (2), Ref Des (R53), Pin Name (2), Pin Use (UNSPEC), Gate Name (F71), Padstack (S_RCT_1-45_X_0-95), Status, and Connections. The Padstack field is highlighted with a red box. On the right is the Search panel, which has a search bar containing 'S_RCT_1-45_X_0-95' (also highlighted with a red box) and a 'Pins (6)' button. Below the search bar is a table with the following data:

X LOCATION	Y LOCATION	GROUP	GATE NAME	PADSTACK	CONNECTION
50.800	55.300		F112	S_RCT_1-45_X_0-95	
52.800	55.300		F112	S_RCT_1-45_X_0-95	
70.131	8.497		F71	S_RCT_1-45_X_0-95	
70.131	6.497		F71	S_RCT_1-45_X_0-95	
70.131	23.975		F70	S_RCT_1-45_X_0-95	

The 'PADSTACK' column in the table is highlighted with a red box.

Allegro Free Physical Viewer

Getting Started with Allegro Free Physical Viewer

Working With Allegro Free Viewer

When reviewing a design, some of the common tasks performed are described in this section.

- [Viewing Objects From Search Results](#)
- [Selecting Objects From Canvas Using Selection Filter](#)
- [Viewing Net Objects in a Design](#)
- [Assigning Color to Net Objects](#)
- [Viewing Object Properties In Datatips](#)
- [Viewing Dynamic Etch Shape Parameters](#)
- [Viewing Pin and Via Parameters](#)
- [Viewing Constraint Resolution Between Two Objects](#)
- [Viewing Design in 3D Canvas](#)
- [Measuring Distance Between Objects](#)
- [Generating Prints](#)
- [Capturing Canvas Image](#)
- [Recording and Replaying Script](#)


Viewing Objects From Search Results

The *Search* panel, by default, displays all the design objects in a spreadsheet format. Different types of objects are displayed in different tabs of that spreadsheet. To choose any object do the following:

1. In *Search* panel, open an object tab.
2. Double-click an object row.

The object is highlighted and zoomed to its location in the design canvas.

3. To select multiple objects, press **CTRL** key and select object rows.



Selecting Objects From Canvas Using Selection Filter




You can choose any object in the design canvas and view its information in the *Properties* panel.

1. Adjust the *Selection Filter* to choose the desired objects.
2. In the design canvas, hover the mouse over an object you want to select.
A datatip displays the object name and attributes.
3. Click to select the object in the canvas.

Allegro Free Physical Viewer

Working With Allegro Free Viewer

The object highlights in the canvas. The *Selection Filter* updates the count of selected object type and *Properties* panel displays the location and other attributes of the selected object.



4. To select multiple objects in the canvas, press **CTRL** key and click to select more objects.

The count of selected objects updates in the *Selection Filter* and *Properties* panel shows only the properties that are common to all the selected objects.

Viewing Net Objects in a Design

All the nets in a design are listed in the *Nets* tab of the *Visibility* panel. To locate and view a specific net in the design do the following:

1. In the *Visibility* panel, open *Nets* tab.
Different sub sections of the tab list all the net objects.
2. Expand the *Diff Pairs* sub section.
3. Double-click a diff pair name to view its member nets.

The following have been updated in the user interface:

- ☐ Both the member nets of diff pair are selected in the design canvas.
- ☐ The *Selection Filter* displays count of Nets.
- ☐ The *Properties* tab displays the location and general properties of nets.
- ☐ The *Constraints* tab of *Properties* panel displays the constraint resolution status.


4. To choose another net object double-click net object name.

Assigning Color to Net Objects

For nets, the color box with default color assignment is displayed in gray color. To assign a color to net, perform the following steps:

1. In the *Visibility* panel open *Nets* tab.
2. Expand the *Nets* sub sections to view all nets.
3. Click the color box of the net you want to assign a color or right-click and choose *Assign Color* option.

A color palette opens to choose a different color and pattern to the net.



4. Pick a new color or choose from *Presets*.


The following changes occurred:

- ☐ The color box starts showing the new color for the net.
- ☐ New assigned color is reflected in all the sub sections for that net.

Allegro Free Physical Viewer

Working With Allegro Free Viewer


- ❑ The color of the parent net also changes.



Note: A rainbow is displayed in the color box of parent net when member nets have different color assigned.

5. To remove the color from the net, right-click the net name and choose *Remove Color*.
6. To clear color assignments on nets, click *Clear All* button for *Net Colors* option.

Note: You can also modify the color of net in the *Properties* panel.



Viewing Object Properties In Datatips


Datatips identifies design element and display information next to the cursor. You can specify the datatip format to display the required information. Do the following to customize the datatips for different object types:

1. Choose *Tools – Datatip Customization* or type `custom datatips` in the command window.

The *Datatips Customization* dialog box opens.

2. Choose an element from the *Object type* list.
3. In the *General* and *Advanced* tabs, enable the name and value check boxes for the information you want to display in datatips.

4. Click *OK* to close the dialog.




Viewing Dynamic Etch Shape Parameters

A dynamic etch shape when selected in the design canvas displays the following parameters in the *Properties* panel:

- General information of the shape
- Shape fill parameters
- Void control parameters
- Thermal relief parameters

In addition to solid fill, a dynamic etch shape can also have cross-hatch fill as illustrated in the following image:




To view parameters of a dynamic shape etch instance, do the following:

1. In the *Selection Filter* of the *Properties* tab, click *All Objects* to disable all the filters.
2. Click *Shapes* to select shape objects.
3. Select a dynamic etch shape in the design canvas.

Allegro Free Physical Viewer

Working With Allegro Free Viewer


The *Properties* panel displays parameters of the selected shape.



Viewing Pin and Via Parameters

When selecting a pin or via in a design canvas, additional parameters are displayed in the *Thermal Reliefs* and *Padstack* section of the *Properties* panel.

Hover the cursor over the  icon, displays the following:



To view properties of a pin or via, do the following:

1. In the *Selection Filter* of the *Properties* tab, click *All Objects* to disable all the filters.
2. Enable either *Pins* or *Vias* or both.
3. Select pins or vias in the design canvas.

Allegro Free Physical Viewer

Working With Allegro Free Viewer

The *Properties* panel displays parameters of the selected pins or vias.

The screenshot shows the Properties panel in Allegro Free Physical Viewer. The panel is divided into several sections:

- General**: Includes fields for Group, Net (+5V), Pin # (20), Ref Des (Z1), Pin Name, Pin Use (POWER), Gate Name, Padstack (PAD60C32P), Status, and Connections (0).
- Thermal Reliefs**: Includes fields for Type, Min/Max, Width, and Value.
- Padstack**: Includes fields for Usage (Through Pin), Hole Type (Circle), Finished Diameter (32 MIL), Plated (Yes), Start/End Layer (TOP, BOTTOM), and Aspect Ratio (1.1875).
- Copper Pad**: Includes fields for Geometry (Circle), Diameter (60 MIL), Annular Ring (14 MIL), Internal (55 MIL), and Annular Ring (11.5 MIL).
- Soldermask Pad**: Includes fields for Geometry (Circle), Diameter (70 MIL), and Annular Ring (19 MIL).


Viewing Constraint Resolution Between Two Objects

When two objects are selected in the design canvas you can view the constraint resolution in the *Constraint* tab of the *Properties* panel.

Allegro Free Physical Viewer

Working With Allegro Free Viewer

1. In the *Selection Filter* of the *Properties* tab, click *All Objects* to disable all the filters.
2. Enable object filter for the objects that you want to check the constraint resolution.
3. Hover over the objects in the design canvas and click to select an object.
4. Press **CTRL** key and click to select one more object of the same type.
5. Open *Constraint* tab in the *Properties* panel.
6. The *Object Constraints* section displays the resolved physical or spacing constraints, constraint set, constraint name and value in a tabular format.



Viewing Design in 3D Canvas


To view the design as a manufactured output you can launch 3D Canvas and analyze the design. You can review all or selective objects in the 3D Canvas.

Allegro Free Physical Viewer

Working With Allegro Free Viewer

Perform the following to open and view design in 3D Canvas:

1. Choose *View – 3D Canvas*.
2. In *3D Canvas Filter*, choose objects and layers and click *OK*.
A progress meter is displayed and designed is launched in the 3D Canvas window.
3. To view internal details of the design in the 3D Canvas, right-click and choose *Cutting Plane*. In the *Options* tab,
 - a. Enable cutting plane options.
 - b. Choose the alignment axis.
 - c. Drag the tilt sliders to change the angle of the cutting plane along the non-aligned axis.



4. To change the appearance of objects and layers in 3D Canvas, choose *Setup – Preferences*.
5. Choose *File – Close* to exit 3D Canvas.

Measuring Distance Between Objects

When reviewing design, you can measure distance between different objects by using keyboard and mouse controls. Do the following to measure distance:

1. Adjust *Selection Filter* to enable the specific object filters.
2. Press and hold **Alt** key.

Shadow mode is temporarily enabled.


3. Click to select an object that you want to measure from.

The object highlights in the canvas.

4. Hover the mouse over object you want to measure to.

The object is temporary highlighted. A rectangle with two cross lines connecting two opposite corners indicates the point on an object where the air gap is measured. The air gap distance between the selected objects is represented by a red dynamic straight line drawn between the centers of the two markers. The air gap measurement displayed in red includes both primary and secondary units.

If the selected object is a pin or via, the center-to-center spacing between them is also displayed in white color, indicated with (c).



5. To choose a different object, hover over another object.

The first object remains the same and the second object changes. The dynamic line also changes and display the air gap between objects.



6. Repeat the above step to choose different objects to dynamically see measured distance values between first object and new objects.
7. To reset the selection of the first object, click on another object.
The object highlights and defined as first object.
8. Hover over another object to display measure.



Tip

To measure distance between segments of a shape, enable *LineSegments* in the Selection Filter.

9. To exit measure mode, release the **Alt** key.

Shadow mode also disables.

Generating Prints

To directly print the design from free viewer, you can use print commands. You can preview the design and setup printing parameters as you do in any other application. Modified parameters are retained in the `.ini` file and applied to every database you open until you change the parameters.

Note: Print commands are available only on Windows platform.

Perform following steps to print a design:

1. Adjust the visibility of the design layers and objects.
2. Zoom to the location which you want to print.
3. Choose *File – Print Setup*.

The *Plot Setup* dialog box opens.

4. Set printing parameters as required and click *OK* to save the settings.
5. Choose *File – Print*.

The Print Review window opens.

6. Expand the Print Review to preview the active design and select the printer icon.
7. Choose a printer name. If you want to direct output to a file, enable *Print to file* check box in the Print window.
8. If necessary, set additional printing options and click *Print*.

Capturing Canvas Image

Saving image of design canvas is important when you want to share your screen with others or want to reference it later. To do this task you can capture an image of design canvas either from a menu option or from the command line. You can save this image in any of the four supported image formats (*.bmp, *.jpg, *.png, and *.tif).

To capture and save the image do the following:

1. Zoom to the location of the design in the canvas which you want to capture.
2. Choose *Tools – Capture Canvas Image* or type `capture image` in the command window.

The *Capture Image* file browser displays.

3. Browse a directory location to save the image.
4. Specify the name of the image file.
5. Choose an image file format and click *Save*.

The image is by default is saved in the current design directory in Bitmap (.bmp) format.

Recording and Replaying Script

1. Choose *File – Script*.

The *Scripting* dialog box displays.

2. In the *Name* text box, enter a name for the script.
3. To create a macro, enable the *Macro Record Mode* check box.
4. Click *Record*.

The *Scripting* dialog box disappears.

5. Perform the tasks that you want the script to run.

The name of the file and the *Rec* status appears in the Status window.

6. Choose *File – Script* again and click *Stop* in the *Scripting* dialog box.

A script file(*.scr*) is saved in the current design directory.

7. To replay a script, do the following:

- a. In the *Scripting* dialog box, click *Browse*.
- b. Choose a script file and click *Open*.
- c. Click *Replay*.

The selected script start running on the design.

Allegro Free Physical Viewer

Working With Allegro Free Viewer

Menus and Commands

The user interface of Allegro Free viewer is simple and consists of logically organized menus that are required to review a design. This section walks you through the menu options and associated commands of free viewer.

File Menu Commands

The File menu includes standard options to open, close and print a design. You can access the following commands:

- open
- plot
- plot setup
- plot preview
- script
- exit

open

Opens an existing design file in the current directory. A file browser lets you search for the specified design file if you do not provide a file name. You can also open a file from the most recently used files using the *File – Recent Designs* menu.

Menu Path

File – Open

File – Recent Designs

Allegro Free Physical Viewer

Menus and Commands

Shortcut Keys

Ctrl+O

Icon



Syntax

```
open [<design to open>]
```

If you do not provide the *<design to open>* argument, a browser window opens in the current directory.

Examples

```
open master.brd
```

The *master.brd* file opens in the current directory.

```
open \boards\master.brd
```

The *master.brd* file, located in the *boards* directory in the current directory, opens.

Open File Browser Dialog Box

The Open dialog box is a standard file browser. You can type the name of the file you want in the *File name* field, or choose the file from the list. Selecting a directory in the list by double clicking on it pushes into the directory.

The *Look in* drop-down allows you to navigate higher in the directory hierarchy. You can drag and drop folders in the *Look in* column to create links to directories. To delete those link a *Remove* option is available on the right-click menu.

The *File of type* field, by default, provides the typical extension of the file required. The drop-down provides access to additional extensions. You can override the extensions by typing a name with one or more wildcard characters in the *File name* field. The preview button displays a simple graphic of the database, the image of which depends on the type of database you are viewing.

plot

The `plot` command on Windows runs the standard *Windows Print* dialog box.

Menu Path

File – Print

Shortcut Keys

Ctrl+P

plot setup

Lets you set parameters for plotting a design.

Menu Path

File – Print Setup

Plot Setup Dialog Box

The parameters set in the *Plot Setup* dialog box are retained in the `.ini` file. Therefore, they remain in effect for every database you open until you change the parameters.

Allegro Free Physical Viewer

Menus and Commands

General Tab

<i>Plot scaling</i>	<p><i>Fit to page:</i> Indicates the plot file is to be scaled to fit the entire plotted page.</p> <p><i>Scaling factor:</i> Indicates the scale of the finished plot.</p> <p><i>Default line weight:</i> Converts any zero width line to a width proportional to the setting. Aids in displaying very thin lines on high-resolution output.</p>
<i>Plot orientation</i>	<p><i>Auto center:</i> Centers the design on the plot page. This control automatically invokes when you choose the Fit to page setting.</p> <p><i>Mirror:</i> Flips the design end-for-end about the Y axis. Useful for viewing top and/or bottom layers.</p>
<i>Plot method</i>	<p><i>Color:</i> Directs the output to print in color. Color is determined by the method specific to the platform you are using. On Unix, color is read from a user-supplied stipples file (<code>allegro_plot_param.stipples</code>); if a stipples file is not found, plotter color defaults are used. On Windows, color selection is determined by setting in the Color and Visibility dialog box.</p> <p><i>Black and white:</i> Directs the output to print in black and white.</p>
<i>Plot contents</i>	<p><i>Screen contents:</i> Prints/plots the contents of what is currently displayed in the design area of the user interface.</p> <p><i>Sheet contents:</i> Prints/plots the extents of all currently-visible graphics within the design (not the drawing extents).</p>
<i>IPF setup</i>	<p><i>Vectorize text:</i> Specifies that text output to the IPF file is broken into line vectors.</p> <p><i>Width:</i> specifies the width for simulating the text characters. The width used is established with the environment variable <code>PLOT_VECTEXT_WIDTH</code>. The default is 0.</p> <p>When <i>Vectorize text</i> is enabled, and a negative value is entered in the <i>Width</i> field, any other width setting of 0 or greater causes photoplot widths to be ignored, and all text is uniformly stroked with the same specified width. The <i>Vectorize text</i> and <i>Width</i> settings apply as specified when the <code>create plot</code> command executes.</p>
<i>OK</i>	Saves the settings and closes the dialog box.
<i>Cancel</i>	Closes the dialog box without saving the settings.

Allegro Free Physical Viewer

Menus and Commands

Windows Tab

Only appears on the Windows platform. The `.ini` file retains all settings between sessions.

Non-vectorized Text Control

Non-Vectorized Text Choose to generate plot files with true font text, which lets you generate PDF-format plot output with researchable text.

Font Specifies a font to use; defaults to Courier.

Font Height Enter a percentage scaling factor for the character height to closely match font text with that of the normal vectorized text display/plot.

Font Width Enter a percentage scaling factor for the character width to closely match font text with that of the normal vectorized text display/plot.

View Available Fonts Click to review the available text fonts for the plot device.

Margin Control

Margin Width Specify the desired margin width in user units. The default equates to 0.25 inches, or 0.0 if the `noplotmargins` environment variable is set.

plot preview

Lets you preview a plot as it will look when printed. This command opens Print Preview window to preview the active design as it will plot based on the setup parameters in the *Plot Setup* dialog box.

Menu Path

File – Print

script

This command records a series of actions. It creates a text file containing the commands that you execute and adds a `.scr` extension to the file name. Using the interactive version of the `script` command that displays the Scripting dialog box, you can also replay the script.

A macro is a script that lets you automate a series of point selections and replay them, starting at another coordinate. When you replay a macro, Allegro Free viewer prompts you for

Allegro Free Physical Viewer

Menus and Commands

a starting point (origin). The macro places the point selections you recorded relative to this starting point. This is useful in performing operations that you need to repeat on a board/ design drawing, such as repeating complex geometric operations.

The current settings in your design are recorded in the script or macro. To display the script with different settings, you must change them as part of the script.

Menu Path

File – Script

Scripting Dialog Box

Script File

Name Specifies the name of the file in which you record your actions. Allegro PCB Editor adds the `.scr` extension to the file name

Browse Displays the script file data browser that lets you choose a script file to replay

Library Displays the script file data browser that lets you choose a script file to replay. Opens to your script path location

Generate Displays a file browser from which you can choose a `.jrl` file to convert into a script without having to leave the current environment. To process the journal file and reconstruct the appropriate script outside of Allegro PCB Editor, run:

```
j2script <source_jrl_file> <target_allegro_script>
```

Macro record mode Specifies whether or not you record as a macro. When replaying, a macro requires a starting point

Record/Replay

Record Starts recording your actions

Stop Stops recording your actions or replaying a script

Replay Starts replaying a macro or script

Cancel Closes the dialog box

Help Displays the Help window

exit

Exits the active layout, closes the application, and returns to the host operating system. Any changes in the design are discarded.

Menu Path

File – Exit

View Menu Commands






The View menu includes standard options to zoom and window settings. You can access the following commands:

- zoom commands
- redraw
- 3d
- show waived drcs
- blank waived drcs
- showhide window commands
- reset dockwindows

Allegro Free Physical Viewer

Menus and Commands

zoom commands

Command Name	Menu Name	Icon	Shortcut Key	Description
zoom points	<i>Zoom By Points</i>			The <code>zoom points</code> command lets you define an area of your layout to zoom in on (magnify).
zoom fit	<i>Zoom Fit</i>		Numeric key (0)	The <code>zoom fit</code> command fits your entire layout in the design window.
zoom in	<i>Zoom In</i>		Numeric key (+)	The <code>zoom in</code> command magnifies your view by a factor of two. You can continue to zoom in on a design by repeating this command. Use dynamic zooming by way of the middle mouse button. A full view of the design, excluding legends and borders, is displayed in the Design window.
zoom out	<i>Zoom Out</i>		Numeric key (-)	The <code>zoom out</code> command halves the magnification of your layout. You can continue to zoom out on a design by repeating this command. Use dynamic zooming by way of the middle mouse button.
zoom world	<i>Zoom World</i>			The <code>zoom world</code> command reduces the magnification of your design so you can view your entire drawing.
zoom center	<i>Zoom Center</i>			The <code>zoom center</code> command moves the indicated point in the drawing into the center of the window display.
zoom previous	<i>Zoom Previous</i>			The <code>zoom previous</code> command lets you to zoom back from the current window extents to the prior view.

redraw

Refreshes the work area.

Menu Path

View – Refresh

Shortcut Keys

F5

Icon



3d

Launches Allegro 3D Canvas, which lets you visualize and analyze a three-dimensional model of a design as a manufactured output. You can also view mechanical objects such as shields, fans, heat sinks and housings.

Menu Path

View – 3D Canvas

Shortcut Keys

Numeric Key 3

Icon



show waived drcs

The `show waived drcs` command lets you display all waived DRC error markers on the board. The command does not waive DRC errors. It rather displays the error markers that exist in the design but are invisible.

This command is the opposite of the `blank waived drcs` command.

Menu Path

View – Waive DRCs – Show

blank waived drcs

The `blank waived drcs` command lets you suppress waived DRC error markers from displaying on the board. The command disappears DRC error markers from the board.

This command is the opposite of the `show waived drcs` command.

Menu Path

View – Waive DRCs – Hide

showhide window commands

These commands toggles the visibility of Allegro Free Viewer windows and panels.

A check mark to the left of a window name menu option in the *View* menu indicates that the window is visible. Clicking a menu option with a check mark, hides the window. When you click the menu option again, the window is displayed at the same position with the same size as earlier. You can dock or undock the window by clicking and dragging it anywhere within or outside the design window. You can also control the visibility of a window by choosing to fold, float, or close the window using the controls at the top-right corner of the window.

Note: To show all window panels in their original positions, use *View – Reset UI to Default* (`reset dockwindows` command).

Command Name	Menu Name	Description
<code>showhide text</code>	<i>Command</i>	Toggles the visibility of the <i>Command</i> window.
<code>showhide enhfind</code>	<i>Search</i>	Toggles the visibility of the <i>Search</i> window.
<code>showhide enhproperties</code>	<i>Properties</i>	Toggles the visibility of the <i>Properties</i> panel.
<code>showhide enhvis</code>	<i>Visibility</i>	Toggles the visibility of the <i>Visibility</i> panel.

Allegro Free Physical Viewer

Menus and Commands

Syntax

showhide enhfind [show] [hide]

showhide_find	Displays or hides the panel, depending on its current state.
show	Displays the panel if it is hidden. If it is already visible, no action occurs.
hide	Hides the panel if it is visible. If it is already hidden, no action occurs.

Menu Path

View – Command

View – Search

View – Properties

View – Visibility

reset dockwindows

Restores the *Command*, *Search*, *Properties*, and *Visibility* window panels to display in their original positions.

Menu Path

View – Reset UI to Default

Syntax

reset_dockwindows

Tools Menu Commands

The Tools menu provides options to view design cross-section data, customizing datatips along with capture screen command.

- capture image
- xsection
- custom datatips

capture image

The capture image command captures the screen shots of the selected part of the design canvas and save in Jpeg (.jpeg) format. The other formats for saving an image are Bitmap file (*.bmp), TIFF (*.tif) and Windows Device Independent Bitmap (*.dib).

When you capture an image a file browser is opened to save the image at a desired location. By default, the command is saved in the working directory.

Menu Path

File – Capture Canvas Image

xsection

Displays the layout Cross-section report, which provides information about each layer defined in your layout.

Menu Path

Tools – Cross-section Report

Icon



custom datatips

Lets you customize a context-sensitive datatip that identifies an element when the cursor hovers over it. The datatip configuration file `custdatatips.cdt` contains default datatip information, which loads in the local `pcbenv` directory when the tool launches. Otherwise, only element names display in datatips.

Menu Path

Tools – Datatip Customization

Datatips Customization Dialog Box

<i>Object type</i>	Choose to customize datatips for clines, nets, symbol instances, pins, vias, or DRCs.
<i>General tab</i>	<p>Lists information to display in a datatip for the element chosen in <i>Object Type</i>.</p> <p>Click to Check the <i>Name</i> box to the right of the information to include it in the datatip; the <i>Value</i> box gets checked automatically, indicating its inclusion in the datatip as well.</p> <p>Select the <i>Value</i> box to only include the alphanumeric character string associated with the information in the datatip, which displays as <code>\$<value></code>, such as <code>\$COMMENT</code> for instance, in <i>Specify DataTips Format</i>.</p> <p>Choose <i>All</i> to display all information available for the chosen element in the datatip.</p>

Allegro Free Physical Viewer

Menus and Commands

Advanced tab

Displays all properties applicable to the chosen *Object Type* and available for inclusion in the datatip.

Select the *Name* box to the right of the information to include it in the datatip; the *Value* box gets checked automatically, indicating its inclusion in the datatip as well.

Select the *Value* box to only include the alphanumeric character string associated with the information in the data tip, which displays as \$<*value*>, such as \$COMMENT for instance, in *Specify DataTips Format*.

Select the *Save* box, which only appears next to the user-defined attributes, to include these properties in the CDT file on saving it.

Select *All* to check the check boxes in the column to display all information available for the chosen element in the data tip.

Note: For Net objects, *Path length* and *Manhattan length* are included in the Advanced tab.

Property filter

Enter whole words or character strings to locate a subset of the properties available for the chosen element. To specify a character string, use the asterisk (*) as a wildcard character. Displays only when the you choose the *Advanced tab*.

Apply filter

Choose to display a subset of the available properties using the string entered in the *Property filter*.

Allegro Free Physical Viewer

Menus and Commands

Specify DataTips Format

Customize the order in which to display datatip information using the following keys:

Up arrow: Appends the selected datatip entry to the line above it.

Down arrow: Appends the selected datatip entry to the line below it.

Left arrow: Transposes the selected datatip entry with that immediately to the left of it (if the first entry in a line is selected, nothing happens).

Right arrow: Transposes the selected datatip entry with that immediately to the right of it (if the last entry in a line is selected, nothing happens).

ENTER: Inserts a line break, and moves all the data tips immediately after the selected space onto the next line when you choose a space between data tip entries on the same line.

BACKSPACE and DELETE: Removes a line break and places all data tips immediately after the selected space on the same line when you choose a space between data tip entries on adjacent lines (line break).

Colors

Click to open Select Color dialog for name and value

Load default CDT file

Loads settings from the default `custdatatips.cdt` file.

Save default CDT file

Saves modifications to the default settings in the `custdatatips.cdt` file.

Load Custom CDT File

Imports your customized datatip settings from an external `.cdt` file and applies them to the current design. A file browser appears with the filter set to `*.cdt` and a list of all `.cdt` files available in the current local working directory. You can manually browse to other directories to open a `.cdt` file. For instance, you may create a file with settings that suit a particular design's requirements; each time you open that design, import settings from that `.cdt` file.

Allegro Free Physical Viewer

Menus and Commands

<i>Save Custom CDT File</i>	Exports the current design's customized datatip settings to an external <code>.cdt</code> file stored in your local working directory. A file browser appears with the filter set to <code>*.cdt</code> and a list of all <code>.cdt</code> files in the current local working directory. You can manually browse to other directories to specify an alternate save location.
<i>OK</i>	Saves settings to the <code>.cdt</code> file currently loaded and closes the dialog box.
<i>Cancel</i>	Closes the dialog box without saving any changes.
<i>Reset to defaults</i>	Removes all datatips customization and restores original settings.

Allegro Free Physical Viewer

Menus and Commands

Troubleshooting

What is the minimum system requirement to install Allegro Free Physical Viewer?

The supported operating systems are:

- Windows 10 (64-bit) Professional, including Dark Theme mode
- Windows 11 (64-bit) Professional and Enterprise
- Windows Server 2016 (All Service Packs)
- Windows Server 2019

Cadence® OrCAD® and Allegro® products do not support Windows 10 Starter and Home Basic. In addition, Windows Server support does not include support for Windows Remote Desktop. Windows RT and Tablets/Phones, including Windows 10 Phone, are also not supported.

Recommended hardware is

- 16 GB RAM
- 50 GB free disk space
- A dedicated graphics card (purchased within the last two years) installed with graphics card drivers updated

Note: Do not install Allegro Free Physical Viewer over any existing Cadence installation. Allegro Free Physical Viewer should not be installed in the same directory with any other Cadence product.

Allegro Free Physical Viewer aborts the installation if Cadence PCB 22.1 is already installed on the system. This includes installing into the same hierarchy as the previous versions of Allegro Free Physical Viewer. You may be required to reboot the computer once the installation has finished.

Note: Allegro Free Physical Viewer does not support silent installation.

What are the different versions of Allegro Free Physical Viewer available?

The following are the different versions of Allegro Free Physical Viewer available for download are:

- Allegro/OrCAD/SIP/MCM Free Physical Viewer 22.1 reads the designs for versions 17.4 and 17.2.
- Allegro/OrCAD/SIP/MCM Free Physical Viewer 17.4 reads the designs for versions 16.x and 17.2.
- Allegro/OrCAD/SIP/MCM Free Physical Viewer 16.6 reads the designs for versions 15.x and 16.6.
- Allegro/OrCAD/SIP/MCM Free Physical Viewer 15.x reads the designs for versions 14.x, 15.0, 15.1, 15.2, 15.5, 15.5.1, and 15.7.

You can download these versions from [Allegro Downloads](#).

Is there any standalone Allegro Free Physical Viewer available for Linux or UNIX OS?

The Linux version of Allegro Free Physical Viewer gets installed with any of the SPB installation. The name of the executable file is `allegro_free_viewer` and is located at `<installation_directory>/tools/bin` folder.

A standalone version of Allegro Free Physical Viewer for Linux or UNIX platforms is not available.

Is it possible to cross-probe between Allegro Design Entry HDL to Allegro Free Physical Viewer?

It is not possible to crossprobe from Allegro Design Entry HDL to Allegro Free Physical Viewer as well as Allegro Design Entry CIS to Allegro Free Physical Viewer. Since Allegro Free Physical Viewer is considered a shareware program, it does not offer all functionalities of the actual product.

What is the difference between Allegro Free Physical Viewer and Allegro Physical Viewer Plus?

Allegro Physical Viewer Plus is a database viewer for Allegro PCB Editor, Allegro PCB SI, and Allegro Package Designer databases (`.brd` and `.mcm`). It is intended for use by the

Allegro Free Physical Viewer Troubleshooting

manufacturing or design engineer to review designs and send comments and markups back to the design owner. This is facilitated through a markup layer that lets the reviewer add comments and markups to the design and email either the entire database or just the markup layer back to the design owner. Only the markup layer can be changed. The design data cannot be modified.

Allegro Physical Viewer Plus also includes the capability to view database constraints through the Constraint Manager system. However, none of the design constraints can be modified.

This product is available on the Windows, UNIX, and Linux operating systems. The Allegro Physical Viewer Plus features include:

- Pan, zoom, colors
- Ratsnest on/off
- Highlight & dehighlight
- Editing on a markup layer
- Show element
- Measure
- Find
- Reports
- Printing and plotting

Allegro Physical Viewer Plus is a licensed product and the Cadence Sales Representative can help you find more details about the Sales Packages included in this product. Allegro Free Physical Viewer on the other hand can be downloaded free from the following location:

https://www.cadence.com/en_US/home/tools/allegro-downloads-start.html

After you install Allegro Free Physical Viewer, refer to the `readme.rtf` file to know the features it supports.

Is there any Allegro Free Physical Viewer available when I install OrCAD and Allegro (SPB) products? If yes, how can I access it?

Yes, Allegro Free Physical Viewer gets installed when installing full-fledged products from SPB installation.

Allegro Free Physical Viewer Troubleshooting

Once the SPB installation is finished, you can:

1. Navigate to installation directory
`<installation_directory>:\Cadence\SPB_22.X\tools\bin`
2. Look for the `allegro_free_viewer` executable

You can either double-click on the executable or invoke it through the command prompt.

Why Allegro Free Physical Viewers 2022 aborts while installing?

If you have Cadence OrCAD and Allegro release 22.1 products installed, Cadence PCB Viewers are already installed in the system and Cadence PCB Viewer 2022 installation will not proceed.

To access:

- Allegro Capture Viewer, use
`<installation_directory>\tools\bin\capture.exe -viewer`
- Allegro PCB Editor viewer, use
`<installation_directory>\tools\bin\allegro_free_viewer.exe`
- Allegro Physical Viewer Plus, use
`<installation_directory>\tools\bin\allegro.exe -viewer`
- APD+/SiP Viewer, use
`<installation_directory>\tools\bin\allegro_free_viewer.exe -sip`

How to enable OpenGL in Allegro Free Physical Viewer?

To enable OpenGL in Allegro Free Physical Viewer, set an environment variable `viewer_useoglgraphics` and restart the application.

By default, OpenGL on Windows is disabled for Allegro Free Physical Viewer.

Can SKILL be run on Allegro Free Physical Viewer?

Allegro Free Physical Viewer cannot use any customization and therefore, the SKILL programs cannot be used with this product.

How to use the Alt key for selecting a single layer in the Visibility panel on Linux machines?

Open Windows Preferences dialog using System – Preferences – Windows menu and set the *Movement Key* to *Super*. You can use both Alt and Control keys for single layer and layer pair selection, respectively.

Error Messages and Solution

Error: This application has failed to start because its side-by-side configuration is incorrect.

This error comes when the system does not have the Microsoft Visual C++ redistributable installed. To resolve this error, install required Microsoft Visual C++ redistributable.

Cadence provides the required versions of Microsoft Visual C++ with the SPB installation. The files are located at `<installation_directory>/tools/mbase` folder.

This location contains two directories:

- vn2005: Microsoft 2005 Redistributable Packages for 32bit and 64bit:
 - ❑ Required for SPB 17.0 or earlier releases (for example, 16.x and 15.x).
 - ❑ The 64bit package is only required for certain Signal Integrity binaries starting with the 16.5 release
- vn2012: Microsoft 2012 Redistributable Packages for 32bit and 64bit
 - ❑ Both packages are required for SPB release 17.0

Installing Cadence software via the Cadence-provided installer does not require these packages. If Cadence SPB software aborts on the startup, you will need to install these packages.

`vc_redist_x86.exe` is a Microsoft Redistributable Package, which installs runtime components required SPB 16.2 onward.

`vc_redist_x64.exe` is a Microsoft Redistributable Package, which installs runtime components required to run 64bit executables.

With SPB 17.4-2019 installation, redistributable files are available for Microsoft 2005 and 2012.

“ERROR (SPMHOD36): Cannot open drawing” reported when opening designs using Allegro/Sip FREE Physical Viewer

This error comes when you try to open a board database (`.brd`) using APD+ Free Physical Viewer or if you try to open a SiP / MCM database using Allegro Free Physical Viewer.

Allegro Free Physical Viewer

Troubleshooting

The correct product options you need to use to open the database without any error message:

- Use Allegro Free Physical Viewer (*Cadence PCB Viewers 2022 – PCB Editor Viewer 2022*) to open and view a *.brd file.
- Use APD+ Free Physical Viewer (*Cadence PCB Viewers 2022 – APD+ Viewer 2022*) to open and view a .sip or .mcm file.

ERROR 1152: Error extracting to the temporary location

This error usually occurs when there is insufficient disk space where the files are being extracted or the installer is corrupted. Check the following conditions in sequence to resolve this error:

1. Ensure enough disk space is available
2. Verify that TEMP folder has write permission
3. Ensure no spaces in the TEMP / TMP variable values, for example, C:/TEMP or C:/TMP.

Try download and install Allegro Free Physical Viewer again.